
USC University of Southern California

USC Viterbi School of Engineering

Remote Desktop Connection and Remote Settings


For security purposes, you **CANNOT** remote into your work computer unless you're connected via **FIRST** from a **VPN Client** on your off-campus computer. Also, your office computer does not accept a remote desktop connection by default. If a remote desktop connection to your office computer is desirable, please read the following:

1. On your desktop, right-click **This PC** shortcut and select **Properties**.
   Note: If there is no shortcut on the desktop, open **File Explorer** and right-click **This PC** in the left pane.






2. This will open the **System** menu then select **Remote Settings** on the left panel.




3. Under **Remote Assistance.** Check **Allow Remote Assistance** connections to this computer.
4. Under **Remote Desktop.** Enable Allow remote connections to this computer.
5. Under **Remote Desktop.** Check Allow connections only computers running **Remote Desktop** with **Network Level Authentication**.
6. Click **Apply** then **OK**.




Once your office computer is set up to accept authorized remote desktop connection:

From a remote **Windows 10** computer,


7. On the **Start Menu** type in **Remote Desktop Connection** & select **Remote Desktop Connection** on the top.



8. Type in yourcomputername.vsoe.usc.edu then click on Connect.



9. To find your computer name, right click on **This PC** & select **Properties.**
10. Under **Computer name, domain, and workgroup settings** look for **Full Computer Name.**
11. You will be prompted to enter your credentials for your computer. Login as you would at work. Enter: **vsoe\username** and **password**.
12. Click **OK**.




13. Once connected, you are able to access your resources on your remote computer.

Remote Desktop Mac


1. Go to the App Store and search for Microsoft Remote Desktop.




2. Click Get to download the app. You will need to enter you Apple ID credentials.
3. Once done, launch the app and click '**+**' icon and select **Add PC** at the top of the **Microsoft Remote Desktop** window.



4. Enter your PC name or IP address.



5. For **User Account**, select **Add User Account**, enter your credentials for your computer. Enter: **vsoe\username** and **password** then click **Add**.



6. To start the connection, double-click on your PC Name thumbnail.



7. Click **Continue**.

